

# Package ‘RLumModel’

January 25, 2018

**Type** Package

**Title** Solving Ordinary Differential Equations to Understand  
Luminescence

**Version** 0.3.0

**Date** 2018-XX-XX

**Author** Johannes Friedrich [aut, trl, cre],  
Sebastian Kreutzer [aut, ths],  
Christoph Schmidt [aut, ths]

**Maintainer** Johannes Friedrich <johannes.friedrich@uni-bayreuth.de>

**Description** A collection of functions to simulate luminescence sig-  
nals in quartz and Al<sub>2</sub>O<sub>3</sub> based on published models.

**Contact** Package Developer Team <developer@model.r-luminescence.de>

**License** GPL-3

**Depends** R (>= 3.4.0), utils, Luminescence (>= 0.7.0)

**Imports** deSolve (>= 1.12), methods, Rcpp

**URL** <https://CRAN.R-project.org/package=RLumModel>

**Collate** RLumModel-package.R RcppExports.R calc\_signal.R  
calc\_concentrations.R create\_DRT.sequence.R  
create\_SAR.sequence.R extract\_pars.R extract\_parameters2FME.R  
fit\_RLumModel2data.R model\_LuminescenceSignals.R read\_SEQ2R.R  
set\_pars.R simulate\_CW\_OSL.R simulate\_heating.R  
simulate\_illumination.R simulate\_irradiation.R  
simulate\_LM\_OSL.R simulate\_pause.R simulate\_RF.R  
simulate\_RF\_and\_heating.R simulate\_TL.R translate\_sequence.R

**RoxygenNote** 6.0.1

**Suggests** FME, knitr, kableExtra, testthat

**VignetteBuilder** knitr

**LinkingTo** Rcpp, RcppArmadillo

**NeedsCompilation** yes

## R topics documented:

RLumModel-package . . . . .	2
ExampleData.FittingTL . . . . .	3
ExampleData.ModelOutput . . . . .	4
extract_parameters2FME . . . . .	5
fit_RLumModel2data . . . . .	6
model_LuminescenceSignals . . . . .	9
read_SEQ2R . . . . .	18

<b>Index</b>	<b>20</b>
--------------	-----------

---

RLumModel-package	<i>Solving Ordinary Differential Equations to Understand Luminescence</i>
-------------------	---

---

## Description

A collection of function to simulate luminescence signals in the mineral quartz based on published models.

## Details

Package:	RLumModel
Type:	Package
Version:	0.2.3
Date:	2017-XX-XX
License:	GPL-3

## Author(s)

### Authors

Johannes Friedrich	University of Bayreuth, Germany
Sebastian Kreutzer	IRAMAT-CRP2A, Universite Bordeaux Montaigne, France
Christoph Schmidt	University of Bayreuth, Germany

### Supervisor

Christoph Schmidt, University of Bayreuth, Germany  
 Sebastian Kreutzer, IRAMAT-CRP2A, Universite Bordeaux Montaigne, France

### Support contact

<developers@model.r-luminescence.de>

**Project source code repository**

<https://github.com/R-Lum/RLumModel>

**Related package projects**

<http://www.r-luminescence.de>

<https://cran.r-project.org/package=Luminescence>

<http://shiny.r-luminescence.de>

<https://cran.r-project.org/package=RLumShiny>

**Package maintainer**

Johannes Friedrich, University of Bayreuth, Germany

<johannes.friedrich@uni-bayreuth.de>

**Acknowledgement**

The work of Johannes Friedrich is gratefully supported by the DFG in framework of the project 'Modelling quartz luminescence signal dynamics relevant for dating and dosimetry' (SCHM 3051/4-1).

---

ExampleData.FittingTL *Example data with TL curves extracted from a TL-SAR protocol (lab code BT1195)*

---

**Description**

Example data with TL curves extracted from a TL-SAR protocol (lab code BT1195)

**Format**

A RLum.Analysis object containing measured TL curves.

**Function version**

0.1.0

**Author(s)**

Johannes Friedrich, University of Bayreuth (Germany)

**See Also**

[modCost](#)

**Examples**

```
data("ExampleData.FittingTL", envir = environment())
```

---

ExampleData.ModelOutput

*Example data (TL curve) simulated with parameter set from Pagonis 2007*

---

**Description**

Example data (TL curve) simulated with parameter set from Pagonis 2007

**Format**

A RLum.Analysis object containing one TL curve as RLum.Data.Curve.

**Function version**

0.1.1

**Note**

This example has only one record (TL). The used sequence was `sequence <- list(IRR = c(temp = 20, dose = 10, DoseRate = 1), TL = c(temp_begin = 20, temp_end = 400, heating_rate = 5))`

**Author(s)**

Johannes Friedrich, University of Bayreuth (Germany)

**Source**

**model\_LuminescenceSignals()**

**References**

Pagonis, V., Chen, R., Wintle, A.G., 2007: Modelling thermal transfer in optically stimulated luminescence of quartz. *Journal of Physics D: Applied Physics* 40, 998-1006.

**Examples**

```
data("ExampleData.ModelOutput", envir = environment())

TL_curve <- get_RLum(model.output, recordType = "TL$", drop = FALSE)

##plot TL curve
plot_RLum(TL_curve)

TL_concentrations <- get_RLum(model.output, recordType = "(TL)", drop = FALSE)
plot_RLum(TL_concentrations)
```

---

`extract_parameters2FME`*Prepare parameters for use with R package FME and function `fit_RLumModel2data`*

---

## Description

Prepare parameters for use with R package FME and function `fit_RLumModel2data`

## Usage

```
extract_parameters2FME(model = NULL, parms = NULL)
```

## Arguments

<code>model</code>	<b>character</b> : set model to be used. Available models are: "Bailey2001", "Bailey2002", "Bailey2004", "Pagonis2007", "Pagonis2008", "Friedrich2017"
<code>parms</code>	<b>list</b> : If an own parameter set is used for 'inverse modelling'.

## Value

This function returns a named **vector** for use with R package FME

## Function version

0.1.1 [2016-05-24] (2018-01-19 09:50:38)

## Author(s)

Johannes Friedrich, University of Bayreuth (Germany),

## References

- Bailey, R.M., 2001. Towards a general kinetic model for optically and thermally stimulated luminescence of quartz. *Radiation Measurements* 33, 17-45.
- Bailey, R.M., 2002. Simulations of variability in the luminescence characteristics of natural quartz and its implications for estimates of absorbed dose. *Radiation Protection Dosimetry* 100, 33-38.
- Bailey, R.M., 2004. Paper I-simulation of dose absorption in quartz over geological timescales and its implications for the precision and accuracy of optical dating. *Radiation Measurements* 38, 299-310.
- Pagonis, V., Chen, R., Wintle, A.G., 2007: Modelling thermal transfer in optically stimulated luminescence of quartz. *Journal of Physics D: Applied Physics* 40, 998-1006.
- Pagonis, V., Wintle, A.G., Chen, R., Wang, X.L., 2008. A theoretical model for a new dating protocol for quartz based on thermally transferred OSL (TT-OSL). *Radiation Measurements* 43, 704-708.

Soetaert K., Petzoldt T., 2010: Inverse Modelling, Sensitivity and Monte Carlo Analysis in R Using Package FME. Journal of Statistical Software, 33, 1-28.

Soetaert, K., Cash, J., Mazzia, F., 2012: Solving differential equations in R. Springer Science & Business Media.

### See Also

[model\\_LuminescenceSignals](#), [sensFun](#), [sensRange](#), [fit\\_RLumModel2data](#)

### Examples

```
## use default model
parms <- extract_parameters2FME(model = "Bailey2001")

## use own parameter set

own_parameters <- list(
  N = c(1e13, 0),
  E = c(1.3, 0),
  s = c(1e12, 0),
  A = c(1e-8, 0),
  B = c(0, 1e-8),
  Th = c(0, 0),
  E_th = c(0, 0),
  k_B = 8.617e-5,
  K = 0,
  model = "customized"
)

parms <- extract_parameters2FME(parms = own_parameters)
```

---

fit_RLumModel2data	<i>Fit model parameters to experimental data</i>
--------------------	--

---

### Description

Fit model parameters to experimental data

### Usage

```
fit_RLumModel2data(model, sequence, seq.step2fit, norm = TRUE,
  lab.dose_rate = 1, simulate_sample_history = FALSE, verbose = FALSE,
  show_structure = FALSE, own_parameters = NULL,
  own_state_parameters = NULL, own_start_temperature = NULL, plot = FALSE,
  ...)
```

## Arguments

model	<b>character (required)</b> : set model to be used. Available models are: "Bailey2001", "Bailey2002", "Bailey2004", "Pagonis2007", "Pagonis2008"
sequence	<b>list (required)</b> : set sequence to model as <b>list</b> or as *.seq file from the Riso sequence editor. To simulate SAR measurements there is an extra option to set the sequence list (cf. details). See <a href="#">model_LuminescenceSignals</a> for a detailed description.
seq.step2fit	<b>numeric (required)</b> : Choose the sequence step number to fit. <b>Note: Only sequence steps with an signal output are allowed! This sequence steps are: RF, TL, OSL, LM-OSL</b>
norm	<b>logical</b> (with default): Argument to normalize the signal. This is recommended when fitting parameters to experimental results.
lab.dose_rate	<b>numeric</b> (with default): laboratory dose rate in XXX Gy/s for calculating seconds into Gray in the *.seq file.
simulate_sample_history	<b>logical</b> (with default): FALSE (with default): simulation begins at laboratory conditions, TRUE: simulations begins at crystallization (all levels 0) process#'
verbose	<b>logical</b> (with default): Verbose mode on/off.
show_structure	<b>logical</b> (with default): Shows the structure of the result. Recommended to show record.id to analyse concentrations.
own_parameters	<p><b>list</b> (with default): This argument allows the user to submit own parameter sets. The <b>list</b> has to contain the following items:</p> <ul style="list-style-type: none"> <li>• N: Concentration of electron- and hole traps [<math>\text{cm}^{-3}</math>]</li> <li>• E: Electron/Hole trap depth [eV]</li> <li>• s: Frequency factor [<math>\text{s}^{-1}</math>]</li> <li>• A: Conduction band to electron trap and valence band to hole trap transition probability [<math>\text{s}^{-1} * \text{cm}^3</math>]. <b>CAUTION: Not every publication uses the same definition of parameter A and B! See vignette "RLumModel - Usage with own parameter sets" for further details</b></li> <li>• B: Conduction band to hole centre transition probability [<math>\text{s}^{-1} * \text{cm}^3</math>].</li> <li>• Th: Photo-eviction constant or photoionisation cross section, respectively</li> <li>• E_th: Thermal assistance energy [eV]</li> <li>• k_B: Boltzman constant 8.617e-05 [eV/K]</li> <li>• W: activation energy 0.64 [eV] (for UV)</li> <li>• K: 2.8e7 (dimensionless constant)</li> <li>• model: "customized"</li> <li>• R (optional): Ionisation rate (pair production rate) equivalent to 1 Gy/s [<math>\text{s}^{-1} * \text{cm}^{-3}</math>]</li> </ul> <p>For further details see Bailey 2001, Wintle 1975, vignette "RLumModel - Using own parameter sets" and example 3.</p>
own_state_parameters	<b>numeric</b> (with default): Some publications (e.g. Pagonis 2009) offer state parameters. With this argument the user can submit this state parameters. <b>Note:</b>

You have to submit the state parameters for the conduction band and the valence band, too. For further details see vignette `"RLumModel - Using own parameter sets"` and example 3.

`own_start_temperature` [numeric](#) (with default): Parameter to control the start temperature (in deg. C) of a simulation. This parameter takes effect only when `'model = "customized"` is choosen.

`plot` [logical](#) (with default): Enables or disables plot output. Recommended: No plot output, because fitting function will run a lot of times.

`...` further arguments and graphical parameters passed to [plot.default](#). See details for further information.

### Value

This function returns a function, which is necessary for further calculations with the package "FME".

### Function version

0.1.0 [2016-04-29] (2018-01-19 09:50:38)

### Author(s)

Johannes Friedrich, University of Bayreuth (Germany)

### References

Soetaert K., Petzoldt T., 2010: Inverse Modelling, Sensitivity and Monte Carlo Analysis in R Using Package FME. Journal of Statistical Software, 33, 1-28.

### See Also

[sensFun](#), [sensRange](#), [model\\_LuminescenceSignals](#), [extract\\_parameters2FME](#)

### Examples

```
sequence <- list(
  TL = c(20, 450, 5),
  IRR = c(20, 5, 0.5),
  TL = c(0, 450, 5))

model <- "Pagonis2007"

parms <- extract_parameters2FME(model = model)

func_FME <- fit_RLumModel2data(
  sequence = sequence,
  model = model,
  seq.step2fit = 3)
```



```

SensR <- FME::sensFun(
  func = func_FME,
  parms = parms,
  sensvar = "signal",
  varscale = 1,
  senspar = c("N1", "s1", "E1"))

plot(
  SensR,
  legpos = "bottomleft",
  xlab = "Temperature [°C]",
  main = "Local Sensitivity Analysis TL")

```

---

model\_LuminescenceSignals

*Model Luminescence Signals*


---

## Description

This function models luminescence signals for quartz based on published physical models. It is possible to simulate TL, (CW-) OSL, RF measurements in a arbitrary sequence. This sequence is defined as a [list](#) of certain abrivations. Furthermore it is possible to load a sequence direct from the Riso Sequence Editor. The output is an [RLum.Analysis](#) object and so the plots are done by the [plot\\_RLum.Analysis](#) function. If a SAR sequence is simulated the plot output can be disabled and SAR analyse functions can be used.

## Usage

```

model_LuminescenceSignals(model, sequence, lab.dose_rate = 1,
  simulate_sample_history = FALSE, plot = TRUE, verbose = TRUE,
  show_structure = FALSE, own_parameters = NULL,
  own_state_parameters = NULL, own_start_temperature = NULL,
  parms_FME = NULL, ...)

```

## Arguments

- |               |   |
|---------------|---|
| model         | <b>character (required)</b> : set model to be used. Available models are: "Bailey2001", "Bailey2002", "Bailey2004", "Pagonis2007", "Pagonis2008", "Friedrich2017" and for own models "customized" (or "customised"). Note: When model = "customized" is set, the argument 'own_parameters' has to be set. |
| sequence      | <b>list (required)</b> : set sequence to model as <a href="#">list</a> or as *.seq file from the Riso sequence editor. To simulate SAR measurements there is an extra option to set the sequence list (cf. details).  |
| lab.dose_rate | <b>numeric (with default)</b> : laboratory dose rate in XXX Gy/s for calculating seconds into Gray in the *.seq file.   |

simulate_sample_history	<b>logical</b> (with default): FALSE (with default): simulation begins at laboratory conditions, TRUE: simulations begins at crystallization (all levels 0) process
plot	<b>logical</b> (with default): Enables or disables plot output
verbose	<b>logical</b> (with default): Verbose mode on/off
show_structure	<b>logical</b> (with default): Shows the structure of the result. Recommended to show record.id to analyse concentrations.
own_parameters	<p><b>list</b> (with default): This argument allows the user to submit own parameter sets. The <b>list</b> has to contain the following items:</p> <ul style="list-style-type: none"> <li>• N: Concentration of electron- and hole traps [<math>\text{cm}^{-3}</math>]</li> <li>• E: Electron/Hole trap depth [eV]</li> <li>• s: Frequency factor [<math>\text{s}^{-1}</math>]</li> <li>• A: Conduction band to electron trap and valence band to hole trap transition probability [<math>\text{s}^{-1} * \text{cm}^3</math>]. <b>CAUTION: Not every publication uses the same definition of parameter A and B! See vignette "RLumModel - Usage with own parameter sets" for further details</b></li> <li>• B: Conduction band to hole centre transition probability [<math>\text{s}^{-1} * \text{cm}^3</math>].</li> <li>• Th: Photo-eviction constant or photoionisation cross section, respectively</li> <li>• E_th: Thermal assistance energy [eV]</li> <li>• k_B: Boltzman constant <math>8.617\text{e-}05</math> [eV/K]</li> <li>• W: activation energy 0.64 [eV] (for UV)</li> <li>• K: <math>2.8\text{e}7</math> (dimensionless constant)</li> <li>• model: "customized"</li> <li>• R (optional): Ionisation rate (pair production rate) equivalent to <math>1 \text{ Gy/s}</math> [<math>\text{s}^{-1} * \text{cm}^{-3}</math>]</li> </ul> <p>For further details see Bailey 2001, Wintle 1975, vignette "RLumModel - Using own parameter sets" and example 3.</p>
own_state_parameters	<b>numeric</b> (with default): Some publications (e.g. Pagonis 2009) offer state parameters. With this argument the user can submit this state parameters. For further details see vignette "RLumModel - Using own parameter sets" and example 3.
own_start_temperature	<b>numeric</b> (with default): Parameter to control the start temperature (in deg. C) of a simulation. This parameter takes effect only when 'model = "customized"' is choosen.
parms_FME	<b>logical</b> or <b>numeric</b> (with default): This argument is only necessary, if fit_data2RLumModel is used. There is no need to change this parameter per hand, all is done automatically. Nevertheless is it necessary for the package "FME" to have the parameters directly in the function call.
...	further arguments and graphical parameters passed to <code>plot.default</code> . See details for further information.

## **Details**

Defining a **sequence**

Arguments	Description	Sub-arguments
TL	thermally stimulated luminescence	'temp begin' [°C], 'temp end' [°C], 'heating rate' [°C/s]
OSL	optically stimulated luminescence	'temp' [°C], 'duration' [s], 'optical_power' [%]
ILL	illumination	'temp' [°C], 'duration' [s], 'optical_power' [%]
LM_OSL	linear modulated OSL	'temp' [°C], 'duration' [s], optional: 'start_power' [%], 'end_power' [%]
RL/RF	radioluminescence	'temp' [°C], 'dose' [Gy], 'dose_rate' [Gy/s]
RF_heating	RF during heating/cooling	'temp begin' [°C], 'temp end' [°C], 'heating rate' [°C/s], 'dose_rate' [Gy/s]
IRR	irradiation	'temp' [°C], 'dose' [Gy], 'dose_rate' [Gy/s]
CH	cutheat	'temp' [°C], optional: 'duration' [s], 'heating_rate' [°C/s]
PH	preheat	'temp' [°C], 'duration' [s], optional: 'heating_rate' [°C/s]
PAUSE	pause	'temp' [°C], 'duration' [s]

Note: 100 % illumination power equates to 20 mW/cm<sup>2</sup>

Defining a **SAR-sequence**

Abrivation	Description	examples
RegDose	Dose points of the regenerative cycles [Gy]	c(0, 80, 140, 260, 320, 0, 80)
TestDose	Test dose for the SAR cycles [Gy]	50
PH	Temperature of the preheat [°C]	240
CH	Temperature of the cutheat [°C]	200
OSL_temp	Temperature of OSL read out [°C]	125
OSL_duration	Duration of OSL read out [s]	default: 40
Irr_temp	Temperature of irradiation [°C]	default: 20
PH_duration	Duration of the preheat [s]	default: 10
dose_rate	Dose rate of the laboratory irradiation source [Gy/s]	default: 1
optical_power	Percentage of the full illumination power [%]	default: 90
Irr_2recover	Dose to be recovered in a dose-recovery-test [Gy]	20

## Value

This function returns an [RLum.Analysis](#) object with all TL, (LM-) OSL and RF/RL steps in the sequence. Every entry is an [RLum.Data.Curve](#) object and can be plotted, analysed etc. with further RLum-functions.

## Function version

0.1.4 (2018-01-19 09:50:38)

## Author(s)

Johannes Friedrich, University of Bayreuth (Germany), Sebastian Kreutzer, IRAMAT-CRP2A, Université Bordeaux Montaigne (France)

## References

Bailey, R.M., 2001. Towards a general kinetic model for optically and thermally stimulated luminescence of quartz. *Radiation Measurements* 33, 17-45.

- Bailey, R.M., 2002. Simulations of variability in the luminescence characteristics of natural quartz and its implications for estimates of absorbed dose. *Radiation Protection Dosimetry* 100, 33-38.
- Bailey, R.M., 2004. Paper I-simulation of dose absorption in quartz over geological timescales and its implications for the precision and accuracy of optical dating. *Radiation Measurements* 38, 299-310.
- Friedrich, J., Kreutzer, S., Schmidt, C., 2016. Solving ordinary differential equations to understand luminescence: 'RLumModel', an advanced research tool for simulating luminescence in quartz using R. *Quaternary Geochronology* 35, 88-100.
- Friedrich, J., Pagonis, V., Chen, R., Kreutzer, S., Schmidt, C., 2017: Quartz radiofluorescence: a modelling approach. *Journal of Luminescence* 186, 318-325.
- Pagonis, V., Chen, R., Wintle, A.G., 2007: Modelling thermal transfer in optically stimulated luminescence of quartz. *Journal of Physics D: Applied Physics* 40, 998-1006.
- Pagonis, V., Wintle, A.G., Chen, R., Wang, X.L., 2008. A theoretical model for a new dating protocol for quartz based on thermally transferred OSL (TT-OSL). *Radiation Measurements* 43, 704-708.
- Pagonis, V., Lawless, J., Chen, R., Anderson, C., 2009. Radioluminescence in Al<sub>2</sub>O<sub>3</sub>:C - analytical and numerical simulation results. *Journal of Physics D: Applied Physics* 42, 175107 (9pp).
- Soetaert, K., Cash, J., Mazzia, F., 2012. Solving differential equations in R. Springer Science & Business Media.
- Wintle, A., 1975. Thermal Quenching of Thermoluminescence in Quartz. *Geophysical Journal International* 41, 107-113.

## See Also

[plot](#), [RLum](#), [read\\_SEQ2R](#)

## Examples

```
##=====##
## Example 1: Simulate Bailey2001
## (cf. Bailey, 2001, Fig. 1)
##=====##

##set sequence with the following steps
## (1) Irradiation at 20 deg. C with a dose of 10 Gy and a dose rate of 1 Gy/s
## (2) TL from 20-400 deg. C with a rate of 5 K/s

sequence <-
  list(
    IRR = c(20, 10, 1),
    TL = c(20, 400, 5)
  )

##model sequence
model.output <- model_LuminescenceSignals(
  sequence = sequence,
```

```

    model = "Bailey2001"
  )

  ##get all TL concentrations

  TL_conc <- get_RLum(model.output, recordType = "(TL)", drop = FALSE)

  plot_RLum(TL_conc)

  ##plot 110 deg. C trap concentration

  TL_110 <- get_RLum(TL_conc, recordType = "conc. level 1")
  plot_RLum(TL_110)

  ##=====##
  ## Example 2: compare different optical powers of stimulation light
  ##=====##

  # call function "model_LuminescenceSignals", model = "Bailey2004"
  # and simulate_sample_history = FALSE (default),
  # because the sample history is not part of the sequence
  # the optical_power of the LED is varied and then compared.

  optical_power <- seq(from = 0,to = 100,by = 20)

  model.output <- lapply(optical_power, function(x){

    sequence <- list(IRR = c(20, 50, 1),
                      PH = c(220, 10, 5),
                      OSL = c(125, 50, x)
                    )

    data <- model_LuminescenceSignals(
      sequence = sequence,
      model = "Bailey2004",
      plot = FALSE,
      verbose = FALSE
    )

    return(get_RLum(data, recordType = "OSL$", drop = FALSE))
  })

  ##combine output curves
  model.output.merged <- merge_RLum(model.output)

  ##plot
  plot_RLum(
    object = model.output.merged,
    xlab = "Illumination time [s]",
    ylab = "OSL signal [a.u.]",
    main = "OSL signal dependency on optical power of stimulation light",
    legend.text = paste("Optical power density", 20*optical_power/100, "mW/cm^2"),
    combine = TRUE)

```

```

##=====##
## Example 3: Usage of own parameter sets (Pagonis 2009)
##=====##

own_parameters <- list(
  N = c(2e15, 2e15, 1e17, 2.4e16),
  E = c(0, 0, 0, 0),
  s = c(0, 0, 0, 0),
  A = c(2e-8, 2e-9, 4e-9, 1e-8),
  B = c(0, 0, 5e-11, 4e-8),
  Th = c(0, 0),
  E_th = c(0, 0),
  k_B = 8.617e-5,
  W = 0.64,
  K = 2.8e7,
  model = "customized",
  R = 1.7e15
)
## Note: In Pagonis 2009 is B the valence band to hole centre probability,
## but in Bailey 2001 this is A_j. So the values of B (in Pagonis 2009)
## are A in the notation above. Also notice that the first two entries in N, A and
## B belong to the electron traps and the last two entries to the hole centres.

own_state_parameters <- c(0, 0, 0, 9.4e15)

## calculate Fig. 3 in Pagonis 2009. Note: The labels for the dose rate in the original
## publication are not correct.
## For a dose rate of 0.1 Gy/s belongs a RF signal to ~ 1.5e14 (see Fig. 6).

sequence <- list(RF = c(20, 0.1, 0.1))

model_LuminescenceSignals(
  model = "customized",
  sequence = sequence,
  own_parameters = own_parameters,
  own_state_parameters = own_state_parameters)

## Not run:
##=====##
## Example 4: Simulate Thermal-Activation-Characteristics (TAC)
##=====##

##set temperature
act.temp <- seq(from = 80, to = 600, by = 20)

##loop over temperature
model.output <- vapply(X = act.temp, FUN = function(x) {

##set sequence, note: sequence includes sample history

```

```

sequence <- list(
  IRR = c(20, 1, 1e-11),
  IRR = c(20, 10, 1),
  PH = c(x, 1),
  IRR = c(20, 0.1, 1),
  TL = c(20, 150, 5)
)
##run simulation
temp <- model_LuminescenceSignals(
  sequence = sequence,
  model = "Pagonis2007",
  simulate_sample_history = TRUE,
  plot = FALSE,
  verbose = FALSE
)
## "TL$" for exact matching TL and not (TL)
TL_curve <- get_RLum(temp, recordType = "TL$")
##return max value in TL curve
return(max(get_RLum(TL_curve)[,2]))
}, FUN.VALUE = 1)

##plot results
plot(
  act.temp[-(1:3)],
  model.output[-(1:3)],
  type = "b",
  xlab = "Temperature [°C]",
  ylab = "TL [a.u.]"
)

#####
## Example 5: Simulate SAR sequence
#####

##set SAR sequence with the following steps
## (1) RegDose: set regenerative dose [Gy] as vector
## (2) TestDose: set test dose [Gy]
## (3) PH: set preheat temperature in deg. C
## (4) CH: Set cutheat temperature in deg. C
## (5) OSL_temp: set OSL reading temperature in deg. C
## (6) OSL_duration: set OSL reading duration in s

sequence <- list(
  RegDose = c(0,10,20,50,90,0,10),
  TestDose = 5,
  PH = 240,
  CH = 200,
  OSL_temp = 125,
  OSL_duration = 70)

# call function "model_LuminescenceSignals", set sequence = sequence,
# model = "Pagonis2007" (palaeodose = 20 Gy) and simulate_sample_history = FALSE (default),
# because the sample history is not part of the sequence

```



```

model.output <- model_LuminescenceSignals(
  sequence = sequence,
  model = "Pagonis2007",
  plot = FALSE
)

# in environment is a new object "model.output" with the results of
# every step of the given sequence.
# Plots are done at OSL and TL steps and the growth curve

# call "analyse_SAR.CWOSL" from RLum package
results <- analyse_SAR.CWOSL(model.output,
  signal.integral.min = 1,
  signal.integral.max = 15,
  background.integral.min = 601,
  background.integral.max = 701,
  fit.method = "EXP",
  dose.points = c(0,10,20,50,90,0,10))

#####
## Example 6: generate sequence from *.seq file and run SAR simulation
#####

# load example *.SEQ file and construct a sequence.
# call function "model_LuminescenceSignals", load created sequence for sequence,
# set model = "Bailey2002" (palaeodose = 10 Gy)
# and simulate_sample_history = FALSE (default),
# because the sample history is not part of the sequence

path <- system.file("extdata", "example_SAR_cycle.SEQ", package="RLumModel")

sequence <- read_SEQ2R(file = path)

model.output <- model_LuminescenceSignals(
  sequence = sequence,
  model = "Bailey2001",
  plot = FALSE
)

## call RLum package function "analyse_SAR.CWOSL" to analyse the simulated SAR cycle

results <- analyse_SAR.CWOSL(model.output,
  signal.integral.min = 1,
  signal.integral.max = 10,
  background.integral.min = 301,
  background.integral.max = 401,
  dose.points = c(0,8,14,26,32,0,8),
  fit.method = "EXP")

print(get_RLum(results))

```

```

#####
## Example 7: Simulate sequence at laboratory without sample history
#####

##set sequence with the following steps
## (1) Irraditation at 20 deg. C with a dose of 100 Gy and a dose rate of 1 Gy/s
## (2) Preheat to 200 deg. C and hold for 10 s
## (3) LM-OSL at 125 deg. C. for 100 s
## (4) Cutheat at 200 dec. C.
## (5) Irraditation at 20 deg. C with a dose of 10 Gy and a dose rate of 1 Gy/s
## (6) Pause at 200 de. C. for 100 s
## (7) OSL at 125 deg. C for 100 s with 90 % optical power
## (8) Pause at 200 deg. C for 100 s
## (9) TL from 20-400 deg. C with a heat rate of 5 K/s
## (10) Radiofluorescence at 20 deg. C with a dose of 200 Gy and a dose rate of 0.01 Gy/s

sequence <-
list(
  IRR = c(20, 100, 1),
  PH = c(200, 10),
  LM_OSL = c(125, 100),
  CH = c(200),
  IRR = c(20, 10, 1),
  PAUSE = c(200, 100),
  OSL = c(125, 100, 90),
  PAUSE = c(200, 100),
  TL = c(20, 400, 5),
  RF = c(20, 200, 0.01)
)

# call function "model_LuminescenceSignals", set sequence = sequence,
# model = "Pagonis2008" (palaeodose = 200 Gy) and simulate_sample_history = FALSE (default),
# because the sample history is not part of the sequence

model.output <- model_LuminescenceSignals(
  sequence = sequence,
  model = "Pagonis2008"
)

## End(Not run)

```

---

read\_SEQ2R

---

*Parse a Risoe SEQ-file to a sequence neccessary for simulating quartz luminescence*


---

## Description

A SEQ-file created by the Risoe Sequence Editor can be imported to simulate the sequence written in the sequence editor.

**Usage**

```
read_SEQ2R(file, lab.dose_rate = 1, txtProgressBar = TRUE)
```

**Arguments**

`file` **character (required)**: a \*.seq file created by the Riso Sequence Editor

`lab.dose_rate` **character** (with default): set the dose rate of the radiation source in the laboratory Gy/s. Default: 1 Gy/s

`txtProgressBar` **logical** (with default): enables or disables the txtProgressBar for a visual control of the progress. Default: txtProgressBar = TRUE

**Details**

**Supported versions:** Supported and tested: version 4.36.

**Value**

This function returns a **list** with the parsed \*.seq file and the required steps for `model_LuminescenceSignals`.

**Function version**

0.1.0 (2017-10-13 13:46:59)

**Author(s)**

Johannes Friedrich, University of Bayreuth (Germany),

**References**

Riso: Sequence Editor User Manual. Available at: [http://www.nutech.dtu.dk/english/-/media/Andre\\_Universitetsenheder/Nutech\\_SequenceEditor.ashx?la=da](http://www.nutech.dtu.dk/english/-/media/Andre_Universitetsenheder/Nutech_SequenceEditor.ashx?la=da)

**See Also**

`model_LuminescenceSignals`, `readLines`

**Examples**

```
##search "example_SAR_cycle.SEQ" in "extdata" in package "RLumModel"
path <- system.file("extdata", "example_SAR_cycle.SEQ", package="RLumModel")

sequence <- read_SEQ2R(file = path, txtProgressBar = FALSE)
```

# Index

## \*Topic **datasets**

ExampleData.FittingTL, [3](#)

ExampleData.ModelOutput, [4](#)

## \*Topic **package**

RLumModel-package, [2](#)

character, [5](#), [7](#), [9](#), [19](#)

ExampleData.FittingTL, [3](#)

ExampleData.ModelOutput, [4](#)

extract\_parameters2FME, [5](#), [8](#)

fit\_RLumModel2data, [5](#), [6](#), [6](#)

list, [5](#), [7](#), [9](#), [10](#), [19](#)

logical, [7](#), [8](#), [10](#), [19](#)

modCost, [3](#)

model.output (ExampleData.ModelOutput),  
[4](#)

model\_LuminescenceSignals, [6–8](#), [9](#), [19](#)

numeric, [7–10](#)

plot, [13](#)

plot.default, [8](#), [10](#)

plot\_RLum.Analysis, [9](#)

read\_SEQ2R, [13](#), [18](#)

readLines, [19](#)

RLum, [13](#)

RLum.Analysis, [9](#), [12](#)

RLum.Data.Curve, [12](#)

RLumModel-package, [2](#)

sensFun, [6](#), [8](#)

sensRange, [6](#), [8](#)

TL\_fitting\_data

(ExampleData.FittingTL), [3](#)

vector, [5](#)